

Instruction Sheet – SmartPAC PRO Firmware Update Quick Start Guide

Updating SmartPAC PRO Firmware via an Email Link from Wintriss Support

Download the SmartPAC PRO firmware update via a link emailed from Wintriss Support (Example link, <http://smartpacpro.com/updates/sppxxxxxxx.zip> with x being the SmartPAC PRO's Serial number). Save the .ZIP file to a USB disk.

Note: Do not unzip the file. The SmartPAC PRO will do that upon starting the update.

Proceed to the SmartPAC PRO and complete the following steps:

1. Starting at the Main Program menu, press the “Initialization Menu” button.
2. Using the “More” button, navigate to “Diagnostics”, press “Enter” and scroll to “Update Firmware”, then press the “Enter” button again.
3. Insert the USB disk with the previously downloaded .ZIP file into the connector on the front of the SmartPAC PRO. When the yellow status box appears, press the “Cancel” button. The status should show: “USB Disk Present”.
4. Press the “Do Update” button. The progress bar will appear and the status will change to “Downloading Firmware”. The download and update process will take approximately 3 minutes.
5. The SmartPAC PRO will restart on its own and return to the Program menu when the update is finished.